

## AUDITION HOW TO

### RECORDING WITH MICROPHONE IN AUDITION

1. SELECT WAVEFORM TAB IN UPPER LEFT CORNER
2. RIGHT CLICK IN LEVELS WINDOW
3. SELECT METER INPUT SIGNAL
4. SET PLAYHEAD TO BEGINNING OF TRACK
5. PRESS RED RECORD BUTTON TO START AND END RECORDING
6. SAVE

### MAKING SELECTIONS

1. SELECT WAVEFORM TAB
2. SELECT SHOW SPECTRAL FREQUENCY DISPLAY
3. USE I-BEAM TO SELECT A PORTION OF WAVE FORM
4. SELECT MARQUEE SELECTION TOOL TO SELECT SPECIFIC FREQUENCIES IN SPECTRAL FREQUENCY DISPLAY
5. SELECT LASSO TOOL TO DRAW A FREEFORM SHAPE AROUND AREA TO EDIT IN SPECTRAL FREQUENCY DISPLAY
6. TO MOVE OR EDIT SELECTION, MOVE POINTER OUTSIDE SELECTION THEN BACK IN. WILL BECOME A HAND. CLICK AND DRAG.

### MANUALLY ADJUST CLIP VOLUME

1. SELECT WAVEFORM TAB
2. PIN HEADS UP DISPLAY AND MOVE TO ONE SIDE
3. DOUBLE CLICK TO SELECT ENTIRE CLIP OR SELECT PORTION OF CLIP
4. SELECT dB IN HEADS UP DISPLAY
5. CLICK AND DRAG LEFT/RIGHT, ENTER VALUE OR USE ARROW KEYS TO RAISE OR LOWER AMPLITUDE

### SAVE AUDIO FROM VIDEO AS MP3

1. SELECT WAVEFORM TAB
2. FILE>IMPORT
  - a. IMPORT VIDEO FILE ON DESKTOP
3. FILE>SAVE AS
  - a. LOCATION: DESKTOP
4. FILE>EXPORT
  - a. LOCATION: DESKTOP
  - b. FORMAT: MP3 (TOONBOOM) OR WAV (PREMIERE PRO)